

**THORMANG3**

# THORMANG3 Tutorial


Module



# Agenda



- Manipulation Module
- Gripper Module
- Walking Module
- Head Control Module
- Feet FT Module



**THORMANG3**

# THORMANG3 Tutorial

Manipulation



# Agenda



- **Robotis Library**
  - robotis\_math
  - thormang3\_kinamtcis\_dynamics
- **Manipulation Module**
  - Overview
    - Structure
    - Files
  - Messages
  - Topic List
  - Programming Guide



- **robotis\_math**

- This library includes basic operations which are used in motion modules.
- These files describes the function related to coordinate transformation.
  - robotis\_math\_base.cpp
  - robotis\_linear\_algebra.cpp

**Eigen::Vector3d** getTransitionXYZ(double position\_x, double position\_y, double position\_z)  
**Eigen::Matrix3d** convertRPYToRotation(double roll, double pitch, double yaw)

- These files illustrate the function for trajectory calculation.
  - robotis\_trajectory\_calculator.cpp
  - bezier\_curve.cpp
  - fifth\_order\_polynomial\_trajectory.cpp
  - simple\_trapezoidal\_velocity\_profile.cpp

**Eigen::MatrixXd** calcMinimumJerkTra( double pos\_start, double vel\_start, double accel\_start,  
double pos\_end, double vel\_end, double accel\_end,  
double smp\_time, double mov\_time )

- This function is used in walking module for step data
  - step\_data\_define.cpp



- **thormang3\_kinematics\_dynamics**

- This library is included in ROBOTIS-THORMAG-MPC package.
- It describes thormang3's kinematics & dynamics information [1].
- We also provide robotics function such as forward & inverse kinematics [1].
- For example, each joint information is written as

**// right arm shoulder roll**

```
thormang3_link_data_[3]->name_           = "r_arm_sh_r";
thormang3_link_data_[3]->parent_          = 1;
thormang3_link_data_[3]->sibling_         = -1;
thormang3_link_data_[3]->child_           = 5;
thormang3_link_data_[3]->mass_            = 0.875;
thormang3_link_data_[3]->relative_position_ = robotis_framework::getTransitionXYZ( 0.057 , -0.060 , -0.039 );
thormang3_link_data_[3]->joint_axis_       = robotis_framework::getTransitionXYZ( -1.0 , 0.0 , 0.0 );
thormang3_link_data_[3]->center_of_mass_   = robotis_framework::getTransitionXYZ( -0.060 , -0.002 , 0.000 );
thormang3_link_data_[3]->joint_limit_max_  = 0.5 * M_PI;
thormang3_link_data_[3]->joint_limit_min_  = -0.5 * M_PI;
thormang3_link_data_[3]->inertia_          = robotis_framework::getInertiaXYZ( 0.00043 , 0.00000 , 0.00000 , 0.00112 , 0.00000 , 0.00113 );
```

[1] Introduction to Humanoid Robotics | Shuuji Kajita | Springer




# Manipulation Module



- Overview

- Structure





# Manipulation Module



- **Overview**

- Files
  - ./src/manipulation\_module.cpp
  - ./include/thormang3\_manipulation\_module/manipulation\_module.h
  - ./config/ik\_weight.yaml
    - > inverse kinematics weight value
  - ./config/ini\_pose.yaml
    - > joint initial pose





# Manipulation Module



- **Messages**
  - manipulation\_module\_msgs
    - msg
      - JointPose.msg
      - KinematicsPose.msg
    - srv
      - GetJointPose.srv
      - GetKinematicsPose.srv



# Manipulation Module



- **Messages (msg)**

- JointPose.msg

- string      name      -> joint name to control
    - float64    value      -> desired joint value [rad]
    - float64    time        -> desired movement time [sec]

- KinematicsPose.msg

- string      name      -> group name such as left arm or right arm
    - geometry\_msgs/Pose -> desired pose (position xyz and orientation xyzw)
    - float64    time        -> desired movement time [sed]



# Manipulation Module



- **Messages (srv)**

- GetJointPose.srv

- request :  
string joint\_name -> If you request joint name,
    - response :  
float64 joint\_value -> it returns present joint value [rad].

- GetKinematicsPose.srv

- request :  
string group\_name -> If you request group name,
    - response :  
geometry\_msgs/Pose group\_pose -> it returns present group pose.



# Manipulation Module



- Topic List

	Name		Description
Topic (Publish)	/robotis/status		publisher to send status
	/robotis/movement_done		publisher to send movement done
Topic (Subscribe)	/robotis/manipulation/ini_pose_msg		command for moving to initial pose
	/robotis/manipulation/joint_pose_msg		command for writing desired angle
	/robotis/manipulation/kinematics_pose_msg		command for writing desired end effector's pose
Service (Server)	/robotis/manipulation/get_joint_pose	req	name for user specified joint
		res	current angle if user specified joint
	/robotis/manipulation/get_kinemtacis_pose	req	name for user specified group
		res	current pose for user specified group




- **Programming guide**
  - Send desired pose
    - Joint pose
    - Kinematics pose
  - Get current pose
    - Read joint pose
    - Read kinematics pose



# Manipulation Module



- **Programming guide**
  - Send desired pose





# Manipulation Module



- **Programming guide**
  - Read current pose

## ROS Framework Function

```
void initialize( ... )
void queueThread( ... )
void stop( ... )
bool isRunning( ... )
void process( ... )
```

## Callback Function

```
void iniPoseMsgCallback( ... )
void jointPoseMsgCallback( ... )
void kinematicsPoseMsgCallback( ... )

bool getJointPoseCallback( ... )
bool getKinematicsPoseCallback( ... )
```

## 1. Receive Service

JointPose Service:  
**GetJointPose.srv**

KinematicsPose Service :  
**GetKinematicsPose.srv**

## 2. to GUI

**Joint name & Joint Value**


**Group name & Kinematics Pose**

## Calculation Function

```
void iniposeTraGeneProc( )
void jointTraGeneProc( )
void taskTraGeneProc( )

void parseData( ... )
void parseIniPoseData( ... )

void setInverseKinematics( ... )
```



**THORMANG3**

# THORMANG3 Tutorial

Gripper





# Agenda




- **Gripper Module**
  - Overview
    - Structure
    - Files
  - Messages
  - Topic List
  - Programming Guide



- Overview

- Structure





# Gripper Module



- **Overview**

- Files
  - `./src/gripper_module.cpp`
  - `./include/thormang3_gripper_module/gripper_module.h`



# Gripper Module



- **Messages**

- In gripper module, we only use general ROS message.
  - msg
    - sensor\_msgs/JointState msg



# Gripper Module



- **Messages (msg)**

- JointState.msg
  - string[] name -> joint name to control
  - float64[] position -> desired joint value [rad]
  - float64[] effort -> goal torque limit



# Gripper Module



- Topic List

	Name	Description
Topic (Publish)	/robotis/status	publisher to send status
	/robotis/movement_done	publisher to send movement done
	/robotis/sync_write_item	Publisher to set goal torque limit
Topic (Subscribe)	/robotis/gripper/joint_pose_msg	command for moving to gripper



# Gripper Module




- **Programming guide**
  - Send desired pose
    - Joint pose




# Gripper Module



- **Programming guide**
  - Send desired pose







**THORMANG3**

# THORMANG3 Tutorial

Walking



# Agenda





- **Robotis Library**
  - thormang3\_balance\_control
- **Robotis ROS Package**
  - thormang3\_foot\_step\_generator
- **Walking Module**
  - Overview
    - Structure
    - Files
  - Messages
  - Topic List
  - Programming Guide



- **thormang3\_balance\_control**

- This library indicates sensory feedback algorithm for THORMANG3.
- In sensory feedback, FT sensors and IMU sensor are used.
- Our balance algorithm is based on PD control.






# Robotis ROS Package



- **thormang3\_foot\_step\_generator**

- This package is used to generate foot step for thormang3's walking module

1. Make step data message
2. Send step data
3. Request reference step data



1. Calculation process



# Robotis ROS Package




- **thormang3\_foot\_step\_generator**
  - Messages
    - FootStepCommand.msg
    - Step2D.msg
    - Step2DArray.msg



# Walking Module



- Overview
  - Structure






# Walking Module



- Overview

- Structure

- thormang3\_online\_walking is generally called as Dr. Kajita's preview walking control which is based on cart-table model





# Walking Module



- **Overview**

- Files

- `./src/walking_module.cpp`
    - `./src/thormang3_online_walking.cpp`
    - `./include/thormang3_walking_module/walking_module.h`
    - `./include/thormang3_walking_module/thormang3_online_walking.h`





- **Messages**

- manipulation\_module\_msgs

- msg

- BalanceParam.msg
      - DampingBalanceParam.msg
      - JointFeedBackGain.msg
      - PoseXYZRPY.msg
      - PoseZRPY.msg
      - RobotPose.msg
      - StepData.msg
      - StepPositionData.msg
      - StepTimeData.msg

- srv

- AddStepDataArray.srv
      - GetReferenceStepData.srv
      - IsRunning.srv
      - RemoveExistingStepData.srv
      - SetBalanceParam.srv
      - SetDampingBalanceParam.srv
      - SetJointFeedBackGain.srv
      - StartWalking.srv



# Walking Module



- Topic List

	Name		Description
<b>Topic (Publish)</b>	/robotis/walking/status_message		The status message from walking module
<b>Service (Server)</b>	/robotis/walking/get_reference_step_data	req	Empty
		res	Reference Step Data
	/robotis/walking/add_step_data	req	"Auto Start" and "Step Data Array"
		res	Processing Result for Request
	/robotis/walking/walking_start	req	Empty
		res	Processing Result for Request
	/robotis/walking/remove_existing_step_data	req	Empty
		res	Processing Result for Request
	/robotis/walking/set_balance_param	req	All of Desired Balancing Parameter
		res	Processing Result for Request
	/robotis/walking/is_running	req	Empty
		res	Running or Not



# Walking Module



- **Programming guide**
  - Set Balance Parameter
  - Send Walking Command




# Walking Module



- **Programming guide**

- Set Balance Parameter





# Walking Module



- **Programming guide**

- balance\_param.yaml

```
##### cob_offset #####
```

```
cob_x_offset_m : -0.015
```

```
cob_y_offset_m : 0.0
```

```
##### FeedForward #####
```

```
hip_roll_swap_angle_rad : 0.0
```

```
##### Gain #####
```

```
# by gyro
```

```
foot_roll_gyro_p_gain : 0.5
```

```
foot_roll_gyro_d_gain : 0.0
```

```
foot_pitch_gyro_p_gain : 0.5
```

```
foot_pitch_gyro_d_gain : 0.0
```

```
# by imu
```

```
foot_roll_angle_p_gain : 1.0
```

```
foot_roll_angle_d_gain : 0.1
```

```
foot_pitch_angle_p_gain : 1.0
```

```
foot_pitch_angle_d_gain : 0.1
```

```
# by ft sensor
```

```
foot_x_force_p_gain : 0.1
```

```
foot_x_force_d_gain : 0.0
```

```
foot_y_force_p_gain : 0.1
```

```
foot_y_force_d_gain : 0.0
```

```
foot_z_force_p_gain : 0.02
```

```
foot_z_force_d_gain : 0.0
```

```
foot_roll_torque_p_gain : 0.0015
```

```
foot_roll_torque_d_gain : 0.0
```

```
foot_pitch_torque_p_gain : 0.0015
```

```
foot_pitch_torque_d_gain : 0.0
```

```
##### CUT OFF FREQUENCY #####
```

```
# by gyro
```

```
roll_gyro_cut_off_frequency : 50.0
```

```
pitch_gyro_cut_off_frequency : 50.0
```

```
# by imu
```

```
roll_angle_cut_off_frequency : 50.0
```

```
pitch_angle_cut_off_frequency : 50.0
```

```
# by ft sensor
```

```
foot_x_force_cut_off_frequency : 40.0
```

```
foot_y_force_cut_off_frequency : 40.0
```

```
foot_z_force_cut_off_frequency : 40.0
```

```
foot_roll_torque_cut_off_frequency : 40.0
```

```
foot_pitch_torque_cut_off_frequency : 40.0
```



- **Programming guide**
  - joint\_feedback\_gain.yaml

```
r_leg_hip_y_p_gain : 1.0      l_leg_hip_y_p_gain : 1.0
r_leg_hip_y_d_gain : 0.0      l_leg_hip_y_d_gain : 0.0

r_leg_hip_r_p_gain : 1.5      l_leg_hip_r_p_gain : 1.5
r_leg_hip_r_d_gain : 0.0      l_leg_hip_r_d_gain : 0.0

r_leg_hip_p_p_gain : 0.15     l_leg_hip_p_p_gain : 0.15
r_leg_hip_p_d_gain : 0.0      l_leg_hip_p_d_gain : 0.0

r_leg_kn_p_p_gain  : 0.15     l_leg_kn_p_p_gain  : 0.15
r_leg_kn_p_d_gain  : 0.0      l_leg_kn_p_d_gain  : 0.0

r_leg_an_p_p_gain  : 0.05     l_leg_an_p_p_gain  : 0.05
r_leg_an_p_d_gain  : 0.0      l_leg_an_p_d_gain  : 0.0

r_leg_an_r_p_gain  : 0.05     l_leg_an_r_p_gain  : 0.05
r_leg_an_r_d_gain  : 0.0      l_leg_an_r_d_gain  : 0.0
```



# Walking Module



- **Programming guide**
  - Send Walking Command

thormang3\_demo



## 1. Send Message

FootStepCommand.msg or Step2DArray.msg

thormang3\_foot\_step\_generator

- Make step data msg
- Send step data msg
- Request reference step data



## 2. Add foot step data

thormang3\_walking\_module



- **Programming guide**

- Send Walking Command

- FootStepCommand.msg

- |           |                  |   |
|-----------|------------------|---|
| – string  | command          | -> walking direction                            |
| – int32   | step_num         | -> step number                                  |
| – float64 | step_length      | -> step length                                  |
| – float64 | side_step_length | -> side step length                             |
| – float64 | step_angle_rad   | -> step angle when the robot turn left or right |

## Programming example : go forward

```
thormang3_foot_step_generator::FootStepCommand msg;  
msg.command = "forward";  
msg.step_num = 3;  
msg.step_length = 0.05;  
msg.side_step_length = 0.0;  
msg.step_angle_rad = 0.0;
```





# Walking Module



- **Programming guide**

- Send Walking Command

- Step2DArray.msg

- Step2D[] footsteps\_2d

-> foot step array

- Step2D.msg

- geometry\_msgs/Pose2D step2d

-> foot step pose


- unit8 moving\_foot


-> moving state

- unit8 LEFT\_FOOT\_SWING = 1

- unit8 RIGHT\_FOOT\_SWING = 2

- unit8 STANDING = 3





**THORMANG3**

# THORMANG3 Tutorial

Head Control



# Agenda



- **Robotis Library**
  - robotis\_math
- **Robotis ROS Package**
  - thormang3\_sensors
- **Head Control Module**
  - Overview
    - Structure
    - Files
  - Messages
  - Topic List
  - Programming Guide



- **robotis\_math**

- This library includes basic operations which are used in motion modules.
- These files describes the function related to coordinate transformation.
  - robotis\_math\_base.cpp
  - robotis\_linear\_algebra.cpp

**Eigen::Vector3d** getTransitionXYZ(double position\_x, double position\_y, double position\_z)  
**Eigen::Matrix3d** convertRPYToRotation(double roll, double pitch, double yaw)

- These files illustrate the function for trajectory calculation.
  - robotis\_trajectory\_calculator.cpp
  - bezier\_curve.cpp
  - fifth\_order\_polynomial\_trajectory.cpp
  - simple\_trapezoidal\_velocity\_profile.cpp

**Eigen::MatrixXd** calcMinimumJerkTra( double pos\_start, double vel\_start, double accel\_start,  
double pos\_end, double vel\_end, double accel\_end,  
double smp\_time, double mov\_time )


- This function is used in walking module for step data
  - step\_data\_define.cpp



- **thormang3\_sensor**

- This package is used to assembling Laserscan(LaserScan to PointCloud)

1. Receive start message
2. Store time of getting start message
3. Receive end message
4. Assemble LaserScan using [laser\\_scan\\_assembler node](#)






# Head Control Module



- Overview

- Structure





# Head Control Module



- **Overview**

- Files

- `./src/head_control_module.cpp`
    - `./include/thormang3_head_control_module/head_control_module.h`



# Head Control Module



- **Messages**

- head\_control\_module\_msgs
  - msg
    - HeadJointPose.msg
- sensor\_msgs
  - msg
    - JointState.msg
- std\_msgs
  - msg
    - String.msg
    - Float64.msg





# Head Control Module



- **Messages (msg)**

- HeadJointPose.msg

- float64                      mov\_time                      -> time to move
    - sensor\_msgs/JointState      angle                      -> desired joint value of head [rad]

- JointState.msg

- String[]                      name                      -> joint name
    - float64[]                      position                      -> desired joint value [rad]
    - float64[]                      velocity                      -> not used
    - float64[]                      effort                      -> not used



# Head Control Module



- Topic List

	Name	Description
<b>Topic (Publish)</b>	<code>/robotis/sensor/move_lidar</code>	Send a topic(start/end time of movement) to the assemble_lidar_node
<b>Topic (Subscribe)</b>	<code>/robotis/head_control/move_lidar</code>	Command to move head pitch joint by a given amount in order to make pointcloud
	<code>/robotis/head_control/move_lidar_with_range</code>	Command to move head pitch joint in order to make pointcloud
	<code>/robotis/head_control/set_joint_states</code>	Command to move joints of head
	<code>/robotis/head_control/set_joint_states_time</code>	Command to move joints of head in given time



# Head Control Module




- **Programming guide**
  - Send desired pose of head joints
    - Set head joints
    - Set head joints with moving time
  - Send command to make pointcloud
    - Make pointcloud of full range
    - Make pointcloud of given range



# Head Control Module



- **Programming guide**
  - Send desired pose of head joints






# Head Control Module



- **Programming guide**

- Send command to make pointcloud






# Head Control Module



- **Programming guide**

- Send command to make pointcloud







# Head Control Module



- **Programming guide**
  - Send command to make pointcloud
    - White line : LaserScan (lidar)
    - Colorful line : PointCloud





**THORMANG3**

# THORMANG3 Tutorial

Feet FT





# Agenda




- **Feet FT Module**
  - Hardware
  - Overview
    - Structure
    - Files
  - Messages
  - Topic List
  - Programming Guide



# THORMANG3 FT Sensor



- Hardware





# THORMANG3 FT Sensor



## • Hardware

- thormang3\_manager/config/THORMANG3.robot


```
[ port info ]
# PORT NAME | BAUDRATE | DEFAULT JOINT
/dev/ttyUSB0 | 2000000 | r_arm_sh_p1
/dev/ttyUSB1 | 2000000 | l_arm_sh_p1
/dev/ttyUSB2 | 2000000 | r_leg_hip_y
/dev/ttyUSB3 | 2000000 | l_leg_hip_y
```

```
[ device info ]
# TYPE | PORT NAME | ID | MODEL | PROTOCOL | DEV NAME | BULK READ ITEMS
dynamixel | /dev/ttyUSB0 | 1 | H54-100-S500-R | 2.0 | r_arm_sh_p1 | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 2 | H54-100-S500-R | 2.0 | l_arm_sh_p1 | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 3 | H54-100-S500-R | 2.0 | r_arm_sh_r | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 4 | H54-100-S500-R | 2.0 | l_arm_sh_r | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 5 | H54-100-S500-R | 2.0 | r_arm_sh_p2 | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 6 | H54-100-S500-R | 2.0 | l_arm_sh_p2 | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 7 | H54-100-S500-R | 2.0 | r_arm_el_y | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 8 | H54-100-S500-R | 2.0 | l_arm_el_y | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 9 | H42-20-S300-R | 2.0 | r_arm_wr_r | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 10 | H42-20-S300-R | 2.0 | l_arm_wr_r | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 11 | H42-20-S300-R | 2.0 | r_arm_wr_y | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 12 | H42-20-S300-R | 2.0 | l_arm_wr_y | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 13 | H42-20-S300-R | 2.0 | r_arm_wr_p | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 14 | H42-20-S300-R | 2.0 | l_arm_wr_p | present_position, present_voltage
dynamixel | /dev/ttyUSB2 | 15 | H54-100-S500-R | 2.0 | r_leg_hip_y | present_position, present_voltage
dynamixel | /dev/ttyUSB3 | 16 | H54-100-S500-R | 2.0 | l_leg_hip_y | present_position, present_voltage
dynamixel | /dev/ttyUSB2 | 17 | H54-200-S500-R | 2.0 | r_leg_hip_r | present_position, present_voltage
dynamixel | /dev/ttyUSB3 | 18 | H54-200-S500-R | 2.0 | l_leg_hip_r | present_position, present_voltage
dynamixel | /dev/ttyUSB2 | 19 | H54-200-B500-R | 2.0 | r_leg_hip_p | present_position, present_voltage
dynamixel | /dev/ttyUSB3 | 20 | H54-200-B500-R | 2.0 | l_leg_hip_p | present_position, present_voltage
dynamixel | /dev/ttyUSB2 | 21 | H54-200-S500-R | 2.0 | r_leg_kn_p | present_position, present_voltage
dynamixel | /dev/ttyUSB3 | 22 | H54-200-S500-R | 2.0 | l_leg_kn_p | present_position, present_voltage
dynamixel | /dev/ttyUSB2 | 23 | H54-200-B500-R | 2.0 | r_leg_an_p | present_position, present_voltage, external_port_data_1, external_port_data_2
dynamixel | /dev/ttyUSB3 | 24 | H54-200-B500-R | 2.0 | l_leg_an_p | present_position, present_voltage, external_port_data_1, external_port_data_2
dynamixel | /dev/ttyUSB2 | 25 | H54-200-S500-R | 2.0 | r_leg_an_r | present_position, present_voltage, external_port_data_1, external_port_data_2, external_port_data_3, external_port_data_4
dynamixel | /dev/ttyUSB3 | 26 | H54-200-S500-R | 2.0 | l_leg_an_r | present_position, present_voltage, external_port_data_1, external_port_data_2, external_port_data_3, external_port_data_4
dynamixel | /dev/ttyUSB0 | 27 | H54-100-S500-R | 2.0 | torso_y | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 28 | H42-20-S300-R | 2.0 | head_y | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 29 | H42-20-S300-R | 2.0 | head_p | present_position, present_voltage
dynamixel | /dev/ttyUSB1 | 30 | GRIPPER | 2.0 | l_arm_grip | present_position, present_voltage
dynamixel | /dev/ttyUSB0 | 31 | GRIPPER | 2.0 | r_arm_grip | present_position, present_voltage
```



- Overview

- Structure





# Feet FT Module



- **Overview**

- Files
  - `./src/feet_force_torque_sensor_module.cpp`
  - `./include/thormang3_feet_ft_module/feet_force_torque_sensor_module.h`



# Feet FT Module



- **Messages**
  - msg
    - BothWrench.msg



# Feet FT Module



- **Messages (msg)**

- BothWrench.msg
  - string      name      -> ft sensor value on the ground or in the air
  - geometry\_msgs/Wrench      right      -> right foot's ft sensor value
  - geometry\_msgs/Wrench      left      -> left foot's ft sensor value



# Feet FT Module



- Topic List

	Name	Description
Topic (Publish)	/robotis/status	publisher to send status
	/robotis/feet_ft/both_ft_value	publisher to send ft sensor's value
Topic (Subscribe)	/robotis/feet_ft/ft_calib_command	command for ft sensor calibration